PODCAST INSTRUCTIONS SEIDMAN COLLEGE OF BUSINESS


Equipment Set-Up

- 1. Remove needed supplies from AUDIO 1 KIT: mic(s), mic stand(s), XLR cord(s), and Zoom L-8 mixing board
- 2. **Mic & Mic Stand**: Squeeze the two metal brackets on the top to expand, insert mic, and plug the XLR cord into the mic (the side with the button)
- 3. **Zoom L-8 mixing board**: plug the XLR cord into the top of the mixing board, working left to right (mics are numbered on the board)
 - a. Plug the mixing board into the computer (the board derives power from the computer, ensure the computer is plugged into a power source)
 - b. Move the channel faders to 0 to reset the board > then adjust volume for the mics and MASTER volume
 - c. Need more help? Open the Zoom L-8 Troubleshooting document (pending)



Podcast Set-Up

- 1. Login to Seidman's reservable laptop or download appropriate software to your device
 - a. 1) Zoom L-8 Driver; and 2) Audacity
- 2. Open Audacity software
- 3. Set Recording Volume to .90
- 4. Set **Recording Device** as Line (ZOOM L-8 Audio)
- 5. Set **Recording Channels** as 1 (Mono) Recording Channel
- 6. Set **Playback Device** as Microsoft Sound Mapper Output





Podcast Recording


- 1. Start recording click **Record** (shortcut: R on the keyboard)
- 2. End recording click Stop


Optimize Recording

- 3. Click Select drop-down > Click All
- 4. Click Effect drop-down > Click Normalize
 - a. Check Remove DC offset (center on 0.0 vertically)
 - b. Check Normalize peak amplitude
 - i. Input 0.0 dB
 - c. Check Normalize stereo channels independently
- 5. Click OK









Save Podcast

- 1. Select File drop-down
- 2. Select Export
- 3. Select **Export as MP3** (i.e., shareable compressed file)
 - a. Save to **Desktop**
 - b. Set Bit Rate Mode as Preset
 - c. Set Quality as Insane, 320 kbps
 - d. Set Channel Mode as Stereo
 - e. Set File name to reflect the podcast topic
 - f. Click Save
- 4. Edit Metadata Tags pop-up
 - a. Input data in the Value column
 - b. Click OK
- 5. Select File drop-down
- 6. Select **Save Project** (i.e., editable file)
 - a. Select Save
 - b. Save to **Desktop**
- 7. Download both files to an external USB flash drive

